Packet Definition

- Must contain terminating characters: "\r\n"
- Maximum length is 34 bytes
 - o 32 bytes for payload
 - o 2 bytes for terminating characters
- No need for padding if less than maximum length
- Begin with 1 decimal digit in ASCII encoding, representing sequence number
- Followed by 3 ASCII characters for the packet type
- Followed by up to 0 to 28 Bytes for the packet's parameters, all digits in ASCII encoding
- Terminated by 2 byte terminating characters
- The following summarises a packet's contents

1 Byte	3 Bytes	0 to 28 Bytes	2 Bytes
Sequence Number	Packet Type	Packet Parameters	"\r\n"

Packet Types

Transport System:

Type	Parameters	Description
ACK	<ack number=""></ack>	Acknowledges the packet with sequence number of
		<ack number=""></ack>
MOV	<distance></distance>	From Controller to Transport:
		Moves the system the 4 digit <distance> in mm. Positive is</distance>
		forwards; negative is backwards.
		From Transport to Controller:
		Confirms system has moved <distance>mm.</distance>
SPD	<speed></speed>	From Controller to Transport:
		Sets the system moving at the 3 digits <speed> in mm/s.</speed>
		Positive is forwards; negative is backwards.
		From to Transport to Controller:
		Confirms system is moving at <speed>mm/s.</speed>

Handler System:

Type	Parameters	Description	
ACK	<ack number=""></ack>	Acknowledges the packet with sequence number of	
		<ack number=""></ack>	
DEG	<joint>,<angle></angle></joint>	> From Controller to Handler:	
		Sets the 1 digit <joint> number to the 3 digit <angle> in</angle></joint>	
		degrees. Only applicable to rotational joints.	
		From Handler to Controller:	
		Confirms <joint> number is set to <angle>°.</angle></joint>	
POS	<joint>,<position></position></joint>	From Controller to Handler:	
		Sets the 1 digit <joint> number to the 3 digit <position> in</position></joint>	
		mm. Only applicable to translational joints.	
		From Handler to Controller:	
		Confirms <joint> number is set to <position>mm.</position></joint>	
ARM	<r>,<θ>,<h></h></r>	From Controller to Handler:	
		Sets the arm to the cylindrical coordinates ($\langle R \rangle, \langle \theta \rangle, \langle H \rangle$)	
		where $\langle R \rangle$ is 3 digits in mm, $\langle \theta \rangle$ is 3 digits in degrees, $\langle H \rangle$	
		is 3 digits in mm.	
		From Handler to Controller:	
		Confirms arm is set to $(\langle R \rangle, \langle \theta \rangle, \langle H \rangle)$ coordinates.	